2016 Presidential Primary – e-Pollbook Addendum

The March 8, 2016 Michigan Presidential Primary requires tracking the voter's ballot selection (Republican, Democratic or a ballot without a Presidential Primary where applicable). This requires temporary changes to certain election and Electronic Pollbook (EPB) procedures detailed below.

Summary of EPB software changes and procedure:

- Auto Advance and Lockout: defaulted to NO for this election. The EPB does not recognize Presidential Primary ballot types as unique ballot styles as they are not related to districts associated with a voter's record
- Ballot Type Selection: an additional selection of Ballot Type must be made when assigning a ballot to a voter

Note: the Ballot Summary procedures have not changed.


Since the **Auto Advance** feature does not have the capability to track Presidential Primary ballot types, **DO NOT** turn this feature on for the Presidential Primary.

The **Lockout** feature may be changed back to Yes if the different ballot types were numbered with unique number sequences in accordance with closed presidential primary ballot production standards. For example:

Lockout – By Ballot Style if (recommended by BOE)		Lockout - None, if	
Republican ballots	1001-1500	Republican ballots	1001-1500
Democratic ballots	2001-2500	Democratic ballots	1001-1500
Ballot w/o Presidential Primary	3001-3500	Ballot w/o Presidential Primary	1001-1500

If your ballot types all start with different numbers, you may change the ballot Lockout default. Log into the EPB software on your laptop and:

- 1. Click File
- 2. Click Options




Processing Voters – Information for Election Inspectors

Voters must select a ballot type for the Presidential Primary. The e-pollbook (EPB) has been modified to record the ballot type with a simple selector screen. Besides the Application to Vote, this is the only place a voter's ballot type should be recorded. The recording of the ballot type will transfer to QVF during the voting history upload performed by the Clerk after the election. No further steps are necessary for logging ballot type.

Completing the Application to Vote/Ballot Selection Form

The Application to Vote has been modified to record the voter's ballot type selection for the Presidential Primary. The voter must complete the SELECT BALLOT TYPE HERE section in order to receive a ballot. If the voter refuses to check a box in this section, a ballot **CAN NOT** be issued.




Assigning a Ballot in the e-Pollbook

- 1. Swipe the voter's driver's license through the magnetic card reader or type the voter's name into the DLN/Name field. If typing, select the correct voter and then you must click on "Lock this voter record"
- 2. Verify that the voter's information provided on the Application to Vote is the same as the information in the EPB. When this verification is complete, click on regular ballot (or Provisional (envelope) or challenged ballot if applicable)
- Issue a ballot 2 Other actions: Record an absentee ballot Regular ballot Provisional (affidavit) ballot Spoil a ballot Provisional (er Issue a ballot Challeng You are about to issue a Regular Ballot to: 5/7/1943 Mcqvf, Andrew David Unlock this voter 0000023 This ballot number will be assigned: Which ballot type is being issued: 3. Find the next available ballot of the voter's Republican Party selected ballot type and enter that ballot Democratic Party Ballot Without Presidential Party 4. Select which ballot type the voter **Æ** OK X Cancel
- number in the ballot number box
- 5. Click OK


requested

- a. If the confirmation window is enabled, the ballot number and ballot type recorded will display in the confirmation screen. Click OK to continue processing the next voter.
- 6. Complete the ELECTION INSPECTOR COMPLETES portion of the Application to Vote with the election inspector's initials, the ballot style type, ballot number and voter number (see example at right)




If absent voter ballots are processed in the precinct, the Ballot Type recorded will show along with the Ballot Number assigned by the clerk in QVF.

Note: If the wrong ballot type is selected in the EPB, the election inspector must go back into the voter's record, select undo, and repeat the steps above selecting the correct ballot type.




Changing the Ballot Type

If the voter decides they want a different ballot type after a ballot has been issued, the voter must change his or her Application to Vote and the new ballot should be processed under the normal spoiled ballot procedures. See the highlighted boxes in the example below for an acceptable way for the voter and election inspector to record the change on the application to vote.




Spoiling a Ballot

- Swipe the voter's driver's license through the magnetic card reader or type the voter's name into the DLN/Name field. If typing, select the correct voter and then you must click on "Lock this voter record"
- 2. Click Spoil a Ballot
- Confirm the ballot number being spoiled and click OK



4. "Lock the voter record" again

- Click a button for the kind of ballot being issued: regular ballot (or Provisional (envelope) or challenged ballot if applicable)
- 6. Record the next available ballot number for the ballot type selected
- 7. Click OK



Ballot Summary

The EPB ballot summary has not changed from previous versions. The Presidential Primary ballot types should be recorded the same way as multiple ballot styles (for example, two or three school districts in one precinct).

Each ballot type is entered on one line in both "A. Number of ballots delivered to precinct" and "J. Number of UNUSED BALLOTS". **Use the Tab key to create a new line.** Only one character can be used for the ballot style. This information is for recording purposes only. Remember, the ballot style line will not calculate until after the cursor is on a new line and/or in a different box.

